
AssertionLib Documentation

Release 3.2.1

B. F. van Beek

Oct 12, 2021

CONTENTS

1	AssertionLib 3.2.1	3
1.1	Installation	3
1.2	Usage	3
2	API	7
2.1	assertionlib	7
2.2	Index	7
	Python Module Index	51
	Index	53

Contents:

ASSERTIONLIB 3.2.1

A package for performing assertions and providing informative exception messages.

1.1 Installation

- PyPi: `pip install AssertionLib`
- GitHub: `pip install git+https://github.com/nlesc-nano/AssertionLib`

1.2 Usage

A comprehensive overview of all available assertion methods is provided in the [documentation](#). A few examples of some basic assertion:

```
>>> import numpy as np
>>> from assertionlib import assertion

# Assert the output of specific callables
>>> assertion.eq(5, 5) # 5 == 5
>>> assertion.lt(5, 6) # 5 < 6
>>> assertion.gt(6, 5) # 5 > 6
>>> assertion.isinstance(5, int)
>>> assertion.hasattr(5, '__init__')
>>> assertion.any([False, False, True])
>>> assertion.isfinite(1.0)

# Simply assert a value
>>> assertion(5 == 5)
>>> assertion(isinstance(5, int))

# Apply post-processing before conducting the assertion
>>> ar_large = np.ones(10)
>>> ar_small = np.zeros(10)
>>> assertion.gt(ar_large, ar_small, post_process=np.all) # all(ar_large > ar_small)

# Perform an assertion which will raise an AssertionError
>>> assertion.eq(5, 6, message='Fancy custom error message') # 5 == 6
Traceback (most recent call last):
...
AssertionError: output = eq(a, b); assert output
```

(continues on next page)

(continued from previous page)

```
exception: AssertionError = AssertionError('Fancy custom error message')

output: bool = False
a: int = 5
b: int = 6
```

A few examples of `AssertionErrors` raised due to incorrect method signatures:

```
>>> from assertionlib import assertion

>>> assertion.len(5)
Traceback (most recent call last):
...
AssertionError: output = len(obj); assert output

exception: TypeError = TypeError("object of type 'int' has no len()")

output: NoneType = None
obj: int = 5
```

```
>>> from assertionlib import assertion

>>> assertion.eq(5, 5, 5, 5)
Traceback (most recent call last):
...
AssertionError: output = eq(a, b, _a, _b); assert output

exception: TypeError = TypeError('eq expected 2 arguments, got 4')

output: NoneType = None
a: int = 5
b: int = 5
_a: int = 5
_b: int = 5
```

A demonstration of the `exception` parameter. Providing an exception type will assert that the provided exception is raised during/before the assertion process:

```
>>> from assertionlib import assertion

>>> len(5)
Traceback (most recent call last):
...
TypeError: object of type 'int' has no len()
```

```
>>> from assertionlib import assertion

>>> assertion.len(5, exception=TypeError) # i.e. len(5) should raise a TypeError
>>> assertion.len([5], exception=TypeError)
Traceback (most recent call last):
...
AssertionError: output = len(obj); assert output

exception: AssertionError = AssertionError("Failed to raise 'TypeError'")

output: int = 1
```

(continues on next page)

(continued from previous page)

```
obj: list = [5]
```

Lastly, the output of custom callables can be asserted in one of the following two ways, supplying the callable to `AssertionManager.assert()` or creating a custom assertion method and adding it to an instance with `AssertionManager.add_to_instance()`:

```
>>> from assertionlib import assertion

>>> def my_fancy_func(a: object) -> bool:
...     return False

# Approach #1, supply to-be asserted callable to assertion.assert_()
>>> assertion.assert_(my_fancy_func, 5)
Traceback (most recent call last):
...
AssertionError: output = my_fancy_func(a); assert output

exception: AssertionError = AssertionError(None)

output: bool = False
a: int = 5
```

```
>>> from assertionlib import assertion

# Approach #2, permanently add a new bound method using assertion.add_to_instance()
>>> assertion.add_to_instance(my_fancy_func)
>>> assertion.my_fancy_func(5)
Traceback (most recent call last):
...
AssertionError: output = my_fancy_func(a); assert output

exception: AssertionError = AssertionError(None)

output: bool = False
a: int = 5
```


2.1 `assertionlib`

A package for performing assertion operations.

2.1.1 `assertionlib.dataclass`

A class with a number of generic pre-defined (magic) methods inspired by the builtin `dataclasses` module introduced in Python 3.7.

2.1.2 `assertionlib.functions`

Various functions related to the `assertionlib.AssertionManager` class.

2.1.3 `assertionlib.manager`

A module containing the actual `assertionlib.AssertionManager` class.

2.1.4 `assertionlib.ndrepr`

A module for holding the `assertionlib.NDRepr` class, a subclass of the builtin `reprlib.Repr` class.

2.2 Index

2.2.1 `assertionlib.manager`

A module containing the actual `AssertionManager` class.

Index

<i>assertion</i>	An instance of <i>AssertionManager</i> .
<i>AssertionManager</i> ([repr_instance])	A class for performing assertions and providing informative exception messages.
<i>AssertionManager.assert</i> (func, *args[, ...])	Perform the following assertion: <code>assert func(*args, **kwargs)</code> .
<i>AssertionManager.__call__</i> (value, *[, ...])	Equivalent to <code>assert value</code> .
<i>AssertionManager.add_to_instance</i> (func[, ...])	Add a new custom assertion method to this instance.

Assertions based on the builtin `operator` module.

<i>AssertionManager.abs</i>	Perform the following assertion: <code>assert abs(a)</code> .
<i>AssertionManager.add</i>	Perform the following assertion: <code>assert add(a, b)</code> .
<i>AssertionManager.and_</i>	Perform the following assertion: <code>assert and_(a, b)</code> .
<i>AssertionManager.concat</i>	Perform the following assertion: <code>assert concat(a, b)</code> .
<i>AssertionManager.contains</i>	Perform the following assertion: <code>assert contains(a, b)</code> .
<i>AssertionManager.countOf</i>	Perform the following assertion: <code>assert countOf(a, b)</code> .
<i>AssertionManager.eq</i>	Perform the following assertion: <code>assert eq(a, b)</code> .
<i>AssertionManager.floordiv</i>	Perform the following assertion: <code>assert floordiv(a, b)</code> .
<i>AssertionManager.ge</i>	Perform the following assertion: <code>assert ge(a, b)</code> .
<i>AssertionManager.getitem</i>	Perform the following assertion: <code>assert getitem(a, b)</code> .
<i>AssertionManager.gt</i>	Perform the following assertion: <code>assert gt(a, b)</code> .
<i>AssertionManager.index</i>	Perform the following assertion: <code>assert index(a)</code> .
<i>AssertionManager.indexOf</i>	Perform the following assertion: <code>assert indexOf(a, b)</code> .
<i>AssertionManager.inv</i>	Perform the following assertion: <code>assert inv(a)</code> .
<i>AssertionManager.invert</i>	Perform the following assertion: <code>assert invert(a)</code> .
<i>AssertionManager.is_</i>	Perform the following assertion: <code>assert is_(a, b)</code> .
<i>AssertionManager.is_not</i>	Perform the following assertion: <code>assert is_not(a, b)</code> .
<i>AssertionManager.le</i>	Perform the following assertion: <code>assert le(a, b)</code> .
<i>AssertionManager.lshift</i>	Perform the following assertion: <code>assert lshift(a, b)</code> .
<i>AssertionManager.lt</i>	Perform the following assertion: <code>assert lt(a, b)</code> .

continues on next page

Table 2 – continued from previous page

<code>AssertionManager.matmul</code>	Perform the following assertion: <code>assert matmul(a, b)</code> .
<code>AssertionManager.mod</code>	Perform the following assertion: <code>assert mod(a, b)</code> .
<code>AssertionManager.mul</code>	Perform the following assertion: <code>assert mul(a, b)</code> .
<code>AssertionManager.ne</code>	Perform the following assertion: <code>assert ne(a, b)</code> .
<code>AssertionManager.neg</code>	Perform the following assertion: <code>assert neg(a)</code> .
<code>AssertionManager.not_</code>	Perform the following assertion: <code>assert not_(a)</code> .
<code>AssertionManager.or_</code>	Perform the following assertion: <code>assert or_(a, b)</code> .
<code>AssertionManager.pos</code>	Perform the following assertion: <code>assert pos(a)</code> .
<code>AssertionManager.pow</code>	Perform the following assertion: <code>assert pow(a, b)</code> .
<code>AssertionManager.rshift</code>	Perform the following assertion: <code>assert rshift(a, b)</code> .
<code>AssertionManager.sub</code>	Perform the following assertion: <code>assert sub(a, b)</code> .
<code>AssertionManager.truediv</code>	Perform the following assertion: <code>assert truediv(a, b)</code> .
<code>AssertionManager.truth</code>	Perform the following assertion: <code>assert truth(a)</code> .
<code>AssertionManager.length_hint</code>	Perform the following assertion: <code>assert length_hint(obj, default=default)</code> .

Assertions based on the builtin `os.path` module.

<code>AssertionManager.isabs</code>	Perform the following assertion: <code>assert isabs(s)</code> .
<code>AssertionManager.isdir</code>	Perform the following assertion: <code>assert isdir(s)</code> .
<code>AssertionManager.isfile</code>	Perform the following assertion: <code>assert isfile(path)</code> .
<code>AssertionManager.islink</code>	Perform the following assertion: <code>assert islink(path)</code> .
<code>AssertionManager.ismount</code>	Perform the following assertion: <code>assert ismount(path)</code> .

Assertions based on the builtin `math` module.

<code>AssertionManager.allclose</code>	Perform the following assertion: <code>assert isclose(a, b, rel_tol=rel_tol, abs_tol=abs_tol)</code> .
<code>AssertionManager.isclose</code>	Perform the following assertion: <code>assert isclose(a, b, rel_tol=rel_tol, abs_tol=abs_tol)</code> .
<code>AssertionManager.isfinite</code>	Perform the following assertion: <code>assert isfinite(x)</code> .

continues on next page

Table 4 – continued from previous page

<code>AssertionManager.isinf</code>	Perform the following assertion: <code>assert isinf(x)</code> .
<code>AssertionManager.isnan</code>	Perform the following assertion: <code>assert isnan(x)</code> .

Assertions based on the builtin `builtins` module.

<code>AssertionManager.callable</code>	Perform the following assertion: <code>assert callable(obj)</code> .
<code>AssertionManager.hasattr</code>	Perform the following assertion: <code>assert hasattr(obj, name)</code> .
<code>AssertionManager.isinstance</code>	Perform the following assertion: <code>assert isinstance(obj, class_or_tuple)</code> .
<code>AssertionManager.issubclass</code>	Perform the following assertion: <code>assert issubclass(cls, class_or_tuple)</code> .
<code>AssertionManager.len</code>	Perform the following assertion: <code>assert len(obj)</code> .
<code>AssertionManager.any</code>	Perform the following assertion: <code>assert any(iterable)</code> .
<code>AssertionManager.all</code>	Perform the following assertion: <code>assert all(iterable)</code> .
<code>AssertionManager.isdisjoint</code>	Perform the following assertion: <code>assert isdisjoint(a, b)</code> .
<code>AssertionManager.issuperset</code>	Perform the following assertion: <code>assert issuperset(a, b)</code> .
<code>AssertionManager.issubset</code>	Perform the following assertion: <code>assert issubset(a, b)</code> .
<code>AssertionManager.round</code>	Perform the following assertion: <code>assert round(number, ndigits=ndigits)</code> .

Miscellaneous assertions.

<code>AssertionManager.len_eq</code>	Perform the following assertion: <code>assert len_eq(a, b)</code> .
<code>AssertionManager.str_eq</code>	Perform the following assertion: <code>assert str_eq(a, b, str_converter=str_converter)</code> .
<code>AssertionManager.shape_eq</code>	Perform the following assertion: <code>assert shape_eq(a, b)</code> .
<code>AssertionManager.function_eq</code>	Perform the following assertion: <code>assert function_eq(func1, func2)</code> .

API

`assertionlib.manager.assertion` : **AssertionManager**

An instance of *AssertionManager*.

class `assertionlib.manager.AssertionManager` (*repr_instance*: *Optional[reprlib.Repr]* = *<assertionlib.ndrepr.NDRepr object>*)

A class for performing assertions and providing informative exception messages.

A number of usage examples are provided in the the [documentation](#).

Parameters *repr_instance* (*reprlib.Repr*, optional) – An instance of *reprlib.Repr* for formatting Exception messages. The passed instance should have access to a bound callable by the name of *repr*, which in turn should produce a string representation of any passed objects. If *None*, default the builtin *repr()* function. See also *AssertionManager.repr_instance*.

repr_instance

An instance of *reprlib.Repr* for formatting Exception messages. The passed instance should have access to a bound callable by the name of *repr*, which in turn should produce a string representation of passed objects. If *None*, default the builtin *repr()* function.

Type *reprlib.Repr*, optional

repr_fallback

A fallback value in case *AssertionManager.repr_instance* is *None*.

Type *Callable[[Any], str]*

maxstring_fallback

A fallback value in case *AssertionManager.repr_instance* is *None*.

Type *int*

`AssertionManager.assert_` (*func*: *Callable[...], T*), **args*: *Any*, *invert*: *bool* = *False*, *exception*: *Optional[Type[Exception]]* = *None*, *post_process*: *Optional[Callable[[T], Any]]* = *None*, *message*: *Optional[str]* = *None*, ***kwargs*: *Any*) → *None*

Perform the following assertion: `assert func(*args, **kwargs)`.

Examples

For example `assert 5 == 5` is equivalent to `AssertionManager().assert_(operator.eq, 5, 5)`.

Parameters

- **func** (*Callable[...], T*) – The callable whose output will be evaluated.
- ***args** (*Any*) – Positional arguments for **func**.

Keyword Arguments

- **invert** (*bool*, optional) – If *True*, invert the output of the assertion: `assert not func(*args, **kwargs)`.
- **exception** (*type [Exception]*, optional) – Assert that **exception** is raised during/before the assertion operation. The only disallowed value is *AssertionError*.
- **post_process** (*Callable[[T], bool]*, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example functions would be the likes of *any()* and *all()*.

- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.
- ****kwargs** (*Any*, optional) – Keyword arguments for **func**.

Return type `None`

See also:

`AssertionManager.__call__()` Equivalent to `assert value`.

`AssertionManager.__call__(value: T, *, invert: bool = False, post_process: Optional[Callable[[T], Any]] = None, message: Optional[str] = None) → None`
Equivalent to `assert value`.

Examples

```
>>> from assertionlib import assertion

>>> assertion(5 == 5)
>>> assertion(5 == 6)
Traceback (most recent call last):
...
AssertionError: output = (value); assert output

exception: AssertionError = 'None'

output: bool = False
value: bool = False
```

Parameters **value** (*T*) – The to-be asserted value.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not value`.
- **post_process** (*Callable[[T], bool]*, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example functions would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

`AssertionManager.add_to_instance(func: Callable, name: Optional[str] = None, override_attr: bool = False) → None`

Add a new custom assertion method to this instance.

The new method name is added to `AssertionManager._PRIVATE_ATTR`.

Parameters **func** (*Callable*) – The callable whose output will be asserted in the to-be created method.

Keyword Arguments

- **name** (*str*, optional) – The name of the new method. If `None`, use the name of **func**.
- **override_attr** (*bool*) – If `False`, raise an `AttributeError` if a method with the same name already exists in this instance.

Return type `None`

Raises `AttributeError` – Raised if `override_attr=False` and a method with the same name already exists in this instance.

Assertions based on the builtin `operator` module

`AssertionManager.abs(a, /, **kwargs: Any) → None`

Perform the following assertion: `assert abs(a)`.

Parameters `a` – The positional-only argument `a` of `abs()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not abs(a)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

abs() Same as `abs(a)`.

`AssertionManager.add(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert add(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `add()`.
- **b** – The positional-only argument `b` of `add()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not add(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

add() Same as `a + b`.

AssertionManager.**and_**(*a, b, /, **kwargs: Any*) → None

Perform the following assertion: `assert and_(a, b)`.

Parameters

- **a** – The positional-only argument *a* of `and_()`.
- **b** – The positional-only argument *b* of `and_()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not and_(a, b)`.
- **exception** (*type [Exception]*, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable[[Any], bool]*, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type None

See also:

`and_()` Same as *a* & *b*.

AssertionManager.**concat**(*a, b, /, **kwargs: Any*) → None

Perform the following assertion: `assert concat(a, b)`.

Parameters

- **a** – The positional-only argument *a* of `concat()`.
- **b** – The positional-only argument *b* of `concat()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not concat(a, b)`.
- **exception** (*type [Exception]*, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable[[Any], bool]*, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type None

See also:

`concat()` Same as *a* + *b*, for *a* and *b* sequences.

AssertionManager.**contains**(*a, b, /, **kwargs: Any*) → None

Perform the following assertion: `assert contains(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `contains()`.
- **b** – The positional-only argument `b` of `contains()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not contains(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`contains()` Same as `b in a` (note reversed operands).

`AssertionManager.countOf(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert countOf(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `countOf()`.
- **b** – The positional-only argument `b` of `countOf()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not countOf(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`countOf()` Return the number of times `b` occurs in `a`.

`AssertionManager.eq(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert eq(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `eq()`.
- **b** – The positional-only argument `b` of `eq()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not eq(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`eq()` Same as `a == b`.

`AssertionManager.floordiv(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert floordiv(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `floordiv()`.
- **b** – The positional-only argument `b` of `floordiv()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not floordiv(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`floordiv()` Same as `a // b`.

`AssertionManager.ge(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert ge(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `ge()`.
- **b** – The positional-only argument `b` of `ge()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not ge(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.

- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`ge()` Same as `a >= b`.

`AssertionManager.getitem(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert getitem(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `getitem()`.
- **b** – The positional-only argument `b` of `getitem()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not getitem(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`getitem()` Same as `a[b]`.

`AssertionManager.gt(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert gt(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `gt()`.
- **b** – The positional-only argument `b` of `gt()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not gt(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.

- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`gt()` Same as `a > b`.

`AssertionManager.index(a, /, **kwargs: Any) → None`

Perform the following assertion: `assert index(a)`.

Parameters **a** – The positional-only argument `a` of `index()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not index(a)`.
- **exception** (*type* [`Exception`], optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable*[[`Any`], `bool`], optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`index()` Same as `a.__index__()`

`AssertionManager.indexOf(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert indexOf(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `indexOf()`.
- **b** – The positional-only argument `b` of `indexOf()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not indexOf(a, b)`.
- **exception** (*type* [`Exception`], optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable*[[`Any`], `bool`], optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`indexOf()` Return the first index of `b` in `a`.

AssertionManager.**inv**(*a*, /, ***kwargs: Any*) → None

Perform the following assertion: `assert inv(a)`.

Parameters *a* – The positional-only argument *a* of `inv()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not inv(a)`.
- **exception** (*type [Exception]*, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable[[Any], bool]*, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type None

See also:

`inv()` Same as `~a`.

AssertionManager.**invert**(*a*, /, ***kwargs: Any*) → None

Perform the following assertion: `assert invert(a)`.

Parameters *a* – The positional-only argument *a* of `invert()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not invert(a)`.
- **exception** (*type [Exception]*, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable[[Any], bool]*, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type None

See also:

`invert()` Same as `~a`.

AssertionManager.**is_**(*a, b*, /, ***kwargs: Any*) → None

Perform the following assertion: `assert is_(a, b)`.

Parameters

- **a** – The positional-only argument *a* of `is_()`.
- **b** – The positional-only argument *b* of `is_()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not is_(a, b)`.

- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`is_()` Same as `a is b`.

`AssertionManager.is_not(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert is_not(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `is_not()`.
- **b** – The positional-only argument `b` of `is_not()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not is_not(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`is_not()` Same as `a is not b`.

`AssertionManager.le(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert le(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `le()`.
- **b** – The positional-only argument `b` of `le()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not le(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.

- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`le()` Same as `a <= b`.

`AssertionManager.lshift(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert lshift(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `lshift()`.
- **b** – The positional-only argument `b` of `lshift()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not lshift(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`lshift()` Same as `a << b`.

`AssertionManager.lt(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert lt(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `lt()`.
- **b** – The positional-only argument `b` of `lt()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not lt(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.

- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`lt()` Same as `a < b`.

`AssertionManager.matmul(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert matmul(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `matmul()`.
- **b** – The positional-only argument `b` of `matmul()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not matmul(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`matmul()` Same as `a @ b`.

`AssertionManager.mod(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert mod(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `mod()`.
- **b** – The positional-only argument `b` of `mod()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not mod(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`mod()` Same as `a % b`.

`AssertionManager.mul(a, b, /, **kwargs: Any) → None`
 Perform the following assertion: `assert mul(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `mul()`.
- **b** – The positional-only argument `b` of `mul()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not mul(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`mul()` Same as `a * b`.

`AssertionManager.ne(a, b, /, **kwargs: Any) → None`
 Perform the following assertion: `assert ne(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `ne()`.
- **b** – The positional-only argument `b` of `ne()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not ne(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`ne()` Same as `a != b`.

`AssertionManager.neg(a, /, **kwargs: Any) → None`

Perform the following assertion: `assert neg(a)`.

Parameters **a** – The positional-only argument `a` of `neg()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not neg(a)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`neg()` Same as `-a`.

`AssertionManager.not_(a, /, **kwargs: Any) → None`

Perform the following assertion: `assert not_(a)`.

Parameters **a** – The positional-only argument `a` of `not_()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not not_(a)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`not_()` Same as `not a`.

`AssertionManager.or_(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert or_(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `or_()`.
- **b** – The positional-only argument `b` of `or_()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not or_(a, b)`.

- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`or_()` Same as `a | b`.

`AssertionManager.pos(a, /, **kwargs: Any) → None`

Perform the following assertion: `assert pos(a)`.

Parameters **a** – The positional-only argument `a` of `pos()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not pos(a)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`pos()` Same as `+a`.

`AssertionManager.pow(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert pow(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `pow()`.
- **b** – The positional-only argument `b` of `pow()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not pow(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`pow()` Same as `a ** b`.

`AssertionManager.rshift(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert rshift(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `rshift()`.
- **b** – The positional-only argument `b` of `rshift()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not rshift(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`rshift()` Same as `a >> b`.

`AssertionManager.sub(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert sub(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `sub()`.
- **b** – The positional-only argument `b` of `sub()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not sub(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

sub() Same as `a - b`.

`AssertionManager.truediv(a, b, /, **kwargs: Any) → None`

Perform the following assertion: `assert truediv(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `truediv()`.
- **b** – The positional-only argument `b` of `truediv()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not truediv(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

truediv() Same as `a / b`.

`AssertionManager.truth(a, /, **kwargs: Any) → None`

Perform the following assertion: `assert truth(a)`.

Parameters **a** – The positional-only argument `a` of `truth()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not truth(a)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

truth() Return `True` if `a` is true, `False` otherwise.

`AssertionManager.length_hint(obj, default=0, /, **kwargs: Any) → None`

Perform the following assertion: `assert length_hint(obj, default=default)`.

Parameters

- **obj** – The positional-only argument `obj` of `length_hint()`.

- **default** – The positional-only argument default of `length_hint()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not length_hint(obj, default=default)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`length_hint()` Return an estimate of the number of items in `obj`. This is useful for presizing containers when building from an iterable. If the object supports `len()`, the result will be exact. Otherwise, it may over- or under-estimate by an arbitrary amount. The result will be an integer `>= 0`.

Assertions based on the builtin `os.path` module

`AssertionManager.isabs(s, /, **kwargs: Any) → None`

Perform the following assertion: `assert isabs(s)`.

Parameters `s` – The positional-only argument `s` of `isabs()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isabs(s)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`isabs()` Test whether a path is absolute

`AssertionManager.isdir(s, /, **kwargs: Any) → None`

Perform the following assertion: `assert isdir(s)`.

Parameters `s` – The positional-only argument `s` of `isdir()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isdir(s)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.

- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`isdir()` Return true if the pathname refers to an existing directory.

`AssertionManager.isfile(path, /, **kwargs: Any) → None`

Perform the following assertion: `assert isfile(path)`.

Parameters `path` – The positional-only argument `path` of `isfile()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isfile(path)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`isfile()` Test whether a path is a regular file

`AssertionManager.islink(path, /, **kwargs: Any) → None`

Perform the following assertion: `assert islink(path)`.

Parameters `path` – The positional-only argument `path` of `islink()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not islink(path)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`islink()` Test whether a path is a symbolic link

`AssertionManager.ismount(path, /, **kwargs: Any) → None`

Perform the following assertion: `assert ismount(path)`.

Parameters `path` – The positional-only argument `path` of `ismount()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not ismount(path)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`ismount()` Test whether a path is a mount point

Assertions based on the builtin `math` module

`AssertionManager.allclose(a, b, /, *, rel_tol=1e-09, abs_tol=0.0, **kwargs: Any) → None`

Perform the following assertion: `assert isclose(a, b, rel_tol=rel_tol, abs_tol=abs_tol)`.

Parameters

- **a** – The positional-only argument `a` of `isclose()`.
- **b** – The positional-only argument `b` of `isclose()`.
- **rel_tol** – The keyword-only argument `rel_tol` of `isclose()`.
- **abs_tol** – The keyword-only argument `abs_tol` of `isclose()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isclose(a, b, rel_tol=rel_tol, abs_tol=abs_tol)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

isclose() Determine whether two floating point numbers are close in value. `rel_tol` maximum difference for being considered “close”, relative to the magnitude of the input values `abs_tol` maximum difference for being considered “close”, regardless of the magnitude of the input values Return True if a is close in value to b, and False otherwise. For the values to be considered close, the difference between them must be smaller than at least one of the tolerances. `-inf`, `inf` and `NaN` behave similarly to the IEEE 754 Standard. That is, `NaN` is not close to anything, even itself. `inf` and `-inf` are only close to themselves.

`AssertionManager.isclose(a, b, /, *, rel_tol=1e-09, abs_tol=0.0, **kwargs: Any) → None`

Perform the following assertion: `assert isclose(a, b, rel_tol=rel_tol, abs_tol=abs_tol)`.

Parameters

- **a** – The positional-only argument `a` of `isclose()`.
- **b** – The positional-only argument `b` of `isclose()`.
- **rel_tol** – The keyword-only argument `rel_tol` of `isclose()`.
- **abs_tol** – The keyword-only argument `abs_tol` of `isclose()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isclose(a, b, rel_tol=rel_tol, abs_tol=abs_tol)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

isclose() Determine whether two floating point numbers are close in value. `rel_tol` maximum difference for being considered “close”, relative to the magnitude of the input values `abs_tol` maximum difference for being considered “close”, regardless of the magnitude of the input values Return True if a is close in value to b, and False otherwise. For the values to be considered close, the difference between them must be smaller than at least one of the tolerances. `-inf`, `inf` and `NaN` behave similarly to the IEEE 754 Standard. That is, `NaN` is not close to anything, even itself. `inf` and `-inf` are only close to themselves.

`AssertionManager.isfinite(x, /, **kwargs: Any) → None`

Perform the following assertion: `assert isfinite(x)`.

Parameters **x** – The positional-only argument `x` of `isfinite()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isfinite(x)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.

- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`isfinite()` Return True if `x` is neither an infinity nor a NaN, and False otherwise.

`AssertionManager.isinf(x, /, **kwargs: Any) → None`

Perform the following assertion: `assert isinf(x)`.

Parameters `x` – The positional-only argument `x` of `isinf()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isinf(x)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`isinf()` Return True if `x` is a positive or negative infinity, and False otherwise.

`AssertionManager.isnan(x, /, **kwargs: Any) → None`

Perform the following assertion: `assert isnan(x)`.

Parameters `x` – The positional-only argument `x` of `isnan()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isnan(x)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`isnan()` Return True if `x` is a NaN (not a number), and False otherwise.

Assertions based on the builtin `builtins` module

`AssertionManager.callable(obj, /, **kwargs: Any) → None`

Perform the following assertion: `assert callable(obj)`.

Parameters `obj` – The positional-only argument `obj` of `callable()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not callable(obj)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`callable()`

Return whether the object is callable (i.e., some kind of function).

Note that classes are callable, as are instances of classes with a `__call__()` method.

`AssertionManager.hasattr(obj, name, /, **kwargs: Any) → None`

Perform the following assertion: `assert hasattr(obj, name)`.

Parameters

- **obj** – The positional-only argument `obj` of `hasattr()`.
- **name** – The positional-only argument `name` of `hasattr()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not hasattr(obj, name)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`hasattr()`

Return whether the object has an attribute with the given name.

This is done by calling `getattr(obj, name)` and catching `AttributeError`.

AssertionManager.**isinstance** (*obj*, *class_or_tuple*, /, ***kwargs*: Any) → None

Perform the following assertion: `assert isinstance(obj, class_or_tuple)`.

Parameters

- **obj** – The positional-only argument `obj` of `isinstance()`.
- **class_or_tuple** – The positional-only argument `class_or_tuple` of `isinstance()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not isinstance(obj, class_or_tuple)`.
- **exception** (*type* [Exception], optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable*[[Any], bool], optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type None

See also:

`isinstance()`

Return whether an object is an instance of a class or of a subclass thereof.

A tuple, as in `isinstance(x, (A, B, ...))`, may be given as the target to check against. This is equivalent to `isinstance(x, A)` or `isinstance(x, B)` or ... etc.

AssertionManager.**issubclass** (*cls*, *class_or_tuple*, /, ***kwargs*: Any) → None

Perform the following assertion: `assert issubclass(cls, class_or_tuple)`.

Parameters

- **cls** – The positional-only argument `cls` of `issubclass()`.
- **class_or_tuple** – The positional-only argument `class_or_tuple` of `issubclass()`.

Keyword Arguments

- **invert** (*bool*) – If `True`, invert the output of the assertion: `assert not issubclass(cls, class_or_tuple)`.
- **exception** (*type* [Exception], optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (*Callable*[[Any], bool], optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (*str*, optional) – A custom error message to-be passed to the `assert` statement.

Return type None

See also:

issubclass()

Return whether 'cls' is a derived from another class or is the same class.

A tuple, as in `issubclass(x, (A, B, ...))`, may be given as the target to check against. This is equivalent to `issubclass(x, A)` or `issubclass(x, B)` or ... etc.

`AssertionManager.len(obj, /, **kwargs: Any) → None`

Perform the following assertion: `assert len(obj)`.

Parameters `obj` – The positional-only argument `obj` of `len()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not len(obj)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

len() Return the number of items in a container.

`AssertionManager.any(iterable, /, **kwargs: Any) → None`

Perform the following assertion: `assert any(iterable)`.

Parameters `iterable` – The positional-only argument `iterable` of `any()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not any(iterable)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

any()

Return `True` if `bool(x)` is `True` for any `x` in the iterable.

If the iterable is empty, return `False`.

`AssertionManager.all(iterable, /, **kwargs: Any) → None`

Perform the following assertion: `assert all(iterable)`.

Parameters `iterable` – The positional-only argument `iterable` of `all()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not all(iterable)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`all()`

Return `True` if `bool(x)` is `True` for all values `x` in the iterable.

If the iterable is empty, return `True`.

`AssertionManager.isdisjoint(a: Iterable[Hashable], b: Iterable[Hashable], /, **kwargs: Any) →`

`None`
Perform the following assertion: `assert isdisjoint(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `isdisjoint()`.
- **b** – The positional-only argument `b` of `isdisjoint()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not isdisjoint(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`isdisjoint()` Check if **a** has no elements in **b**.

`AssertionManager.issuperset(a: Iterable[Hashable], b: Iterable[Hashable], /, **kwargs: Any) →`

`None`
Perform the following assertion: `assert issuperset(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `issuperset()`.

- **b** – The positional-only argument `b` of `issuperset()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not issuperset(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`issuperset()` Check if **a** contains all elements from **b**.

`AssertionManager.issubset(a: Iterable[Hashable], b: Iterable[Hashable], /, **kwargs: Any) → None`
 Perform the following assertion: `assert issubset(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `issubset()`.
- **b** – The positional-only argument `b` of `issubset()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not issubset(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`issubset()` Check if **b** contains all elements in **a**.

`AssertionManager.round(number, /, *, ndigits=None, **kwargs: Any) → None`
 Perform the following assertion: `assert round(number, ndigits=ndigits)`.

Parameters

- **number** – The positional-only argument `number` of `round()`.
- **ndigits** – The keyword-only argument `ndigits` of `round()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not round(number, ndigits=ndigits)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`round()`

Round a number to a given precision in decimal digits.

The return value is an integer if `ndigits` is omitted or `None`. Otherwise the return value has the same type as the number. `ndigits` may be negative.

Miscellaneous assertions

`AssertionManager.len_eq(a: Sized, b: int, /, **kwargs: Any) → None`

Perform the following assertion: `assert len_eq(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `len_eq()`.
- **b** – The positional-only argument `b` of `len_eq()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not len_eq(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`len_eq()` Check if the length of `a` is equivalent to `b`: `len(a) == b`.

`AssertionManager.str_eq(a: T, b: str, /, *, str_converter: Callable[[T], str] = <built-in function repr>, **kwargs: Any) → None`

Perform the following assertion: `assert str_eq(a, b, str_converter=str_converter)`.

Parameters

- **a** – The positional-only argument `a` of `str_eq()`.

- **b** – The positional-only argument `b` of `str_eq()`.
- **str_converter** – The keyword-only argument `str_converter` of `str_eq()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not str_eq(a, b, str_converter=str_converter)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`str_eq()` Check if the string-representation of **a** is equivalent to **b**: `repr(a) == b`.

`AssertionManager.shape_eq(a: numpy.ndarray, b: Union[numpy.ndarray, Tuple[int, ...]], /, **kwargs: Any) → None`

Perform the following assertion: `assert shape_eq(a, b)`.

Parameters

- **a** – The positional-only argument `a` of `shape_eq()`.
- **b** – The positional-only argument `b` of `shape_eq()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not shape_eq(a, b)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`shape_eq()` Check if the shapes of **a** and **b** are equivalent: `a.shape == getattr(b, 'shape', b)`. **b** should be either an object with the `shape` attribute (e.g. a NumPy array) or a `tuple` representing a valid array shape.

`AssertionManager.function_eq(func1: function, func2: function, /, **kwargs: Any) → None`

Perform the following assertion: `assert function_eq(func1, func2)`.

Parameters

- **func1** – The positional-only argument `func1` of `function_eq()`.

- **func2** – The positional-only argument `func2` of `function_eq()`.

Keyword Arguments

- **invert** (`bool`) – If `True`, invert the output of the assertion: `assert not function_eq(func1, func2)`.
- **exception** (`type [Exception]`, optional) – Assert that **exception** is raised during/before the assertion operation.
- **post_process** (`Callable[[Any], bool]`, optional) – Apply post-processing to the to-be asserted data before asserting aforementioned data. Example values would be the likes of `any()` and `all()`.
- **message** (`str`, optional) – A custom error message to-be passed to the `assert` statement.

Return type `None`

See also:

`function_eq()` Check if two functions are equivalent by checking if their `__code__` is identical. **func1** and **func2** should be instances of `FunctionType` or any other object with access to the `__code__` attribute.

2.2.2 assertionlib.ndrepr

A module for holding the `NDRepr` class, a subclass of the builtin `reprlib.Repr` class.

Index

<code>NDRepr(**kwargs)</code>	A subclass of <code>reprlib.Repr</code> with methods for handling additional object types.
-------------------------------	--

Type-specific repr methods:

<code>NDRepr.repr_float</code>	Create a <code>str</code> representation of a <code>float</code> instance.
<code>NDRepr.repr_Exception</code>	Create a <code>str</code> representation of an <code>Exception</code> instance.
<code>NDRepr.repr_Signature</code>	Create a <code>str</code> representation of a <code>Signature</code> instance.
<code>NDRepr.repr_method</code>	Create a <code>str</code> representation of a bound method.
<code>NDRepr.repr_method_descriptor</code>	Create a <code>str</code> representation of an unbound method.
<code>NDRepr.repr_function</code>	Create a <code>str</code> representation of a function.
<code>NDRepr.repr_builtin_function_or_method</code>	Create a <code>str</code> representation of a builtin function or method.
<code>NDRepr.repr_type</code>	Create a <code>str</code> representation of a <code>type</code> object.
<code>NDRepr.repr_module</code>	Create a <code>str</code> representation of a module.
<code>NDRepr.repr_dict_keys</code>	Create a <code>str</code> representation of a <code>KeysView</code> .
<code>NDRepr.repr_dict_values</code>	Create a <code>str</code> representation of a <code>ValuesView</code> .
<code>NDRepr.repr_dict_items</code>	Create a <code>str</code> representation of a <code>ItemsView</code> .
<code>NDRepr.repr_Molecule</code>	Create a <code>str</code> representation of a <code>plams.Molecule</code> instance.

continues on next page

Table 8 – continued from previous page

<code>NDRepr.repr_Settings</code>	Create a <code>str</code> representation of a <code>plams.Settings</code> instance.
<code>NDRepr.repr_Atom</code>	Create a <code>str</code> representation of a <code>plams.Atom</code> instance.
<code>NDRepr.repr_Bond</code>	Create a <code>str</code> representation of a <code>plams.Bond</code> instance.
<code>NDRepr.repr_ndarray</code>	Create a <code>str</code> representation of a <code>numpy.ndarray</code> instance.
<code>NDRepr.repr_DataFrame</code>	Create a <code>str</code> representation of a <code>pandas.DataFrame</code> instance.
<code>NDRepr.repr_Series</code>	Create a <code>str</code> representation of a <code>pandas.Series</code> instance.
<code>NDRepr.repr_Dataset</code>	Create a <code>str</code> representation of a <code>h5py.Dataset</code> instance.

API

class `assertionlib.ndrepr.NDRepr` (**kwargs: `Union[int, Mapping[str, Any]]`)

A subclass of `reprlib.Repr` with methods for handling additional object types.

Has additional methods for handling:

- PLAMS Molecules, Atoms, Bonds and Settings
- NumPy arrays
- Pandas Series and DataFrames
- Callables

Parameters ****kwargs** (*object*) – User-specified values for one or more `NDRepr` instance attributes. An `AttributeError` is raised upon encountering unrecognized keys.

maxSignature

The maximum length of callables' signatures before further parameters are truncated. See also `NDRepr.repr_Signature()`.

Type `int`

maxfloat

The number of to-be displayed `float` decimals. See also `NDRepr.repr_float()`.

Type `int`

maxMolecule

The maximum number of to-be displayed atoms and bonds in PLAMS molecules. See also `NDRepr.repr_Molecule()`.

Type `int`

maxndarray

The maximum number of items in a `numpy.ndarray` row. Passed as argument to the `numpy.printoptions()` function:

- `threshold = self.maxndarray`
- `edgeitems = self.maxndarray // 2`

See also `NDRepr.repr_ndarray()`.

Type `int`

maxSeries

The maximum number of rows per `pandas.Series` instance. Passed as value to `pandas.options.display`.

- `pandas.options.display.max_rows = self.series`

See also `NDRepr.repr_Series()`.

Type `int`

maxDataFrame

The maximum number of rows per `pandas.DataFrame` instance. Passed as values to `pandas.options.display`:

- `pandas.options.display.max_rows = self.maxdataframe`
- `pandas.options.display.max_columns = self.maxdataframe // 2`

See also `NDRepr.repr_DataFrame()`.

Type `int`

np_printoptions

Additional keyword arguments for `numpy.printoptions()`.

Note: Arguments provided herein will take priority over those specified internally in `NDRepr.repr_ndarray()`.

Type `dict`

pd_printoptions

Additional “keyword arguments” for `pandas.options`.

Note: Arguments provided herein will take priority over those specified internally in `NDRepr.repr_DataFrame()` and `NDRepr.repr_Series()`.

Type `dict`

`NDRepr.repr_float` (*obj: float, level: int*) → `str`
 Create a `str` representation of a `float` instance.

`NDRepr.repr_Exception` (*obj: Exception, level: int*) → `str`
 Create a `str` representation of an `:exc`Exception`` instance.

`NDRepr.repr_Signature` (*obj: inspect.Signature, level: int*) → `str`
 Create a `str` representation of a `Signature` instance.

`NDRepr.repr_method` (*obj: builtins.method, level: int*) → `str`
 Create a `str` representation of a bound method.

`NDRepr.repr_method_descriptor` (*obj: builtins.method_descriptor, level: int*) → `str`
 Create a `str` representation of an unbound method.

`NDRepr.repr_function` (*obj: builtins.function, level: int*) → `str`
 Create a `str` representation of a function.

`NDRepr.repr_builtin_function_or_method` (*obj*: `builtins.builtin_function_or_method`, *level*: `int`)
→ str
 Create a `str` representation of a builtin function or method.

`NDRepr.repr_type` (*obj*: `type`, *level*: `int`) → `str`
 Create a `str` representation of a `type` object.

`NDRepr.repr_module` (*obj*: `builtins.module`, *level*: `int`) → `str`
 Create a `str` representation of a module.

`NDRepr.repr_dict_keys` (*obj*: `KeysView[Any]`, *level*: `int`) → `str`
 Create a `str` representation of a `KeysView`.

`NDRepr.repr_dict_values` (*obj*: `ValuesView[Any]`, *level*: `int`) → `str`
 Create a `str` representation of a `ValuesView`.

`NDRepr.repr_dict_items` (*obj*: `ItemsView[Any, Any]`, *level*: `int`) → `str`
 Create a `str` representation of a `ItemsView`.

`NDRepr.repr_Molecule` (*obj*: `scm.plams.mol.molecule.Molecule`, *level*: `int`) → `str`
 Create a `str` representation of a `plams.Molecule` instance.

`NDRepr.repr_Settings` (*obj*: `scm.plams.core.settings.Settings`, *level*: `int`) → `str`
 Create a `str` representation of a `plams.Settings` instance.

`NDRepr.repr_Atom` (*obj*: `scm.plams.mol.molecule.Atom`, *level*: `int`) → `str`
 Create a `str` representation of a `plams.Atom` instance.

`NDRepr.repr_Bond` (*obj*: `scm.plams.mol.molecule.Bond`, *level*: `int`) → `str`
 Create a `str` representation of a `plams.Bond` instance.

`NDRepr.repr_ndarray` (*obj*: `numpy.ndarray`, *level*: `int`) → `str`
 Create a `str` representation of a `numpy.ndarray` instance.

`NDRepr.repr_DataFrame` (*obj*: `pandas.core.frame.DataFrame`, *level*: `int`) → `str`
 Create a `str` representation of a `pandas.DataFrame` instance.

`NDRepr.repr_Series` (*obj*: `pandas.core.series.Series`, *level*: `int`) → `str`
 Create a `str` representation of a `pandas.Series` instance.

`NDRepr.repr_Dataset` (*obj*: `h5py._hl.dataset.Dataset`, *level*: `int`) → `str`
 Create a `str` representation of a `h5py.Dataset` instance.

2.2.3 assertionlib.dataclass

A class with a number of generic pre-defined (magic) methods inspired by `dataclass` of Python 3.7.

Index

<code>AbstractDataClass()</code>	A dataclass with a number of generic pre-defined (magic) methods.
<code>AbstractDataClass.__repr__()</code>	Return a (machine readable) string representation of this instance.
<code>AbstractDataClass.__eq__(value)</code>	Check if this instance is equivalent to value .
<code>AbstractDataClass.__hash__()</code>	Return the hash of this instance.
<code>AbstractDataClass.__copy__()</code>	Return a shallow copy of this instance; see <code>AbstractDataClass.copy()</code> .

continues on next page

Table 9 – continued from previous page

<code>AbstractDataClass.__deepcopy__([memo])</code>	Return a deep copy of this instance; see <code>AbstractDataClass.copy()</code> ’.
<code>AbstractDataClass.copy([deep])</code>	Return a shallow or deep copy of this instance.
<code>AbstractDataClass.as_dict([return_private])</code>	Construct a dictionary from this instance with all non-private instance variables.
<code>AbstractDataClass.from_dict(dct)</code>	Construct a instance of this objects’ class from a dictionary with keyword arguments.
<code>AbstractDataClass.inherit_annotations()</code>	A decorator for inheriting annotations and docstrings.

API

class `assertionlib.dataclass.AbstractDataClass`

A dataclass with a number of generic pre-defined (magic) methods.

Provides methods for:

- String conversion: `AbstractDataClass.__repr__()`.
- Object comparisons: `AbstractDataClass.__eq__()`.
- Hash construction: `AbstractDataClass.__hash__()`.
- Copying: `AbstractDataClass.copy()`, `AbstractDataClass.__copy__()` and `AbstractDataClass.__deepcopy__()`.
- Dictionary interconversion: `AbstractDataClass.as_dict()` and `AbstractDataClass.from_dict()`.
- Inheriting method docstrings and annotations: `AbstractDataClass.inherit_annotations()`.

`__PRIVATE_ATTR`

A class variable with the names of private instance variable. These attributes will be excluded whenever calling `AbstractDataClass.as_dict()`, printing or comparing objects. The set is unfrozen (and added as instance variables) the moment a class instance is initiated.

Type `frozenset [str]` or `set [str]`

`__HASHABLE`

A class variable denoting whether or not class instances are hashable. The `AbstractDataClass.__hash__` method will be unavailable if `False`.

Type `bool`

`__hash`

An attribute for caching the `hash()` of this instance. Only available if `AbstractDataClass.__HASHABLE` is `True`.

Type `int`

`AbstractDataClass.__repr__()` → `str`

Return a (machine readable) string representation of this instance.

The string representation consists of this instances’ class name in addition to all (non-private) instance variables.

Returns A string representation of this instance.

Return type `str`

See also:

AbstractDataClass.***__PRIVATE_ATTR*** A set with the names of private instance variables.

AbstractDataClass.***__repr_fallback*** Fallback function for *AbstractDataClass*.***__repr__*** () incase of recursive calls.

AbstractDataClass.***__str_iterator*** () Return an iterable for the iterating over this instances' attributes.

AbstractDataClass.***__str*** () Returns a string representation of a single **key/value** pair.

AbstractDataClass.***__eq__*** (*value: Any*) → bool

Check if this instance is equivalent to **value**.

The comparison checks if the class type of this instance and **value** are identical and if all (non-private) instance variables are equivalent.

Returns Whether or not this instance and **value** are equivalent.

Return type bool

See also:

AbstractDataClass.***__PRIVATE_ATTR*** A set with the names of private instance variables.

AbstractDataClass.***__eq*** Return if **v1** and **v2** are equivalent.

AbstractDataClass.***__eq_fallback*** Fallback function for *AbstractDataClass*.***__eq__*** () incase of recursive calls.

AbstractDataClass.***__hash__*** () → int

Return the hash of this instance.

The returned hash is constructed from two components: * The hash of this instances' class type. * The hashes of all key/value pairs in this instances' (non-private) attributes.

If an unhashable instance variable is encountered, *e.g.* a *list*, then its *id()* is used for hashing.

This method will raise a *TypeError* if the class attribute *AbstractDataClass*.***__HASHABLE*** is *False*.

See also:

AbstractDataClass.***__PRIVATE_ATTR*** A set with the names of private instance variables.

AbstractDataClass.***__HASHABLE*** Whether or not this class is hashable.

AbstractDataClass.***__hash_fallback*** Fallback function for *AbstractDataClass*.***__hash__*** () incase of recursive calls.

AbstractDataClass.***__hash*** An instance variable for caching the *hash()* of this instance.

AbstractDataClass.***__copy__*** () → AT

Return a shallow copy of this instance; see *AbstractDataClass*.*copy()*.

AbstractDataClass.***__deepcopy__*** (*memo: Optional[Dict[int, Any]] = None*) → AT

Return a deep copy of this instance; see *AbstractDataClass*.*copy()*.”.

AbstractDataClass.***copy*** (*deep: bool = False*) → AT

Return a shallow or deep copy of this instance.

Parameters **deep** (bool) – Whether or not to return a deep or shallow copy.

Returns A new instance constructed from this instance.

Return type *AbstractDataClass*

`AbstractDataClass.as_dict` (*return_private: bool = False*) → Dict[str, Any]

Construct a dictionary from this instance with all non-private instance variables.

The returned dictionary values are shallow copies.

Parameters `return_private` (bool) – If `True`, return both public and private instance variables. Private instance variables are defined in `AbstractDataClass._PRIVATE_ATTR`.

Returns A dictionary with keyword arguments for initializing a new instance of this class.

Return type dict [str, Any]

See also:

`AbstractDataClass.from_dict` () Construct a instance of this objects' class from a dictionary with keyword arguments.

`AbstractDataClass._PRIVATE_ATTR` A set with the names of private instance variables.

classmethod `AbstractDataClass.from_dict` (*dct: Mapping[str, Any]*) → AT

Construct a instance of this objects' class from a dictionary with keyword arguments.

Parameters `dct` (Mapping [str, Any]) – A dictionary with keyword arguments for constructing a new `AbstractDataClass` instance.

Returns A new instance of this object's class constructed from `dct`.

Return type `AbstractDataClass`

See also:

`AbstractDataClass.as_dict` () Construct a dictionary from this instance with all non-private instance variables.

classmethod `AbstractDataClass.inherit_annotations` () → Callable[[FT], FT]

A decorator for inheriting annotations and docstrings.

Can be applied to methods of `AbstractDataClass` subclasses to automatically inherit the docstring and annotations of identical-named functions of its superclass.

References to `AbstractDataClass` are replaced with ones pointing to the respective subclass.

Returns A decorator for updating the annotations and docstring of a callable.

Return type type

Examples

```
>>> class SubClass (AbstractDataClass) :
...     @AbstractDataClass.inherit_annotations ()
...     def __copy__ (self) : pass
>>> print (SubClass.__copy__.__doc__)
Return a shallow copy of this instance; see :meth:`SubClass.copy`.
>>> print (SubClass.__copy__.__annotations__)
{'self': ~AT, 'return': ~AT}
```

2.2.4 assertionlib.functions

Various functions related to the *AssertionManager* class.

Index

<code>get_sphinx_domain(func[, module_mapping])</code>	Create a Sphinx domain for func .
<code>create_assertion_doc(func)</code>	Create a new NumPy style assertion docstring from the docstring of func .
<code>bind_callable(class_type, func[, name, warn])</code>	Take a callable and use it to create a new assertion method for class_type .
<code>to_positional(func)</code>	Decorate a function's <code>__signature__</code> such that all positional-or-keyword arguments are changed to either positional- or keyword-only.

API

`assertionlib.functions.get_sphinx_domain` (*func*: Callable, *module_mapping*: Mapping[str, str] = mappingproxy({'genericpath': 'os.path', 'posixpath': 'os.path', '_operator': 'operator'}))
→ str

Create a Sphinx domain for **func**.

Examples

```
>>> from collections import OrderedDict
>>> from assertionlib.functions import get_sphinx_domain

>>> value1: str = get_sphinx_domain(int)
>>> print(value1)
:class:`int<python:int>`

>>> value2: str = get_sphinx_domain(list.count)
>>> print(value2)
:meth:`list.count()<python:list.count>`

>>> value3: str = get_sphinx_domain(OrderedDict)
>>> print(value3)
:class:`~collections.OrderedDict`

>>> value4: str = get_sphinx_domain(OrderedDict.keys)
>>> print(value4)
:meth:`~collections.OrderedDict.keys`
```

Parameters

- **func** (Callable) – A class or (builtin) method or function.
- **module_mapping** (dict [str, str]) – A dictionary for mapping `__module__` values to actual module names. Useful for whenever there is a discrepancy between the two, e.g. the *genericpath* module of `os.path.join()`.

Returns A string with a valid Sphinx referring to **func**.

Return type `str`

Raises `TypeError` – Raised if `func` is neither a class or a (builtin) function or method.

`assertionlib.functions.create_assertion_doc` (*func: Callable*) → `str`
 Create a new NumPy style assertion docstring from the docstring of `func`.

The summary of `funcs`' docstring, if available, is added to the "See also" section, in addition with an intersphinx-compatible link to `func`.

Examples

```
>>> from assertionlib.functions import create_assertion_doc

>>> docstring: str = create_assertion_doc(isinstance)
>>> print(docstring)
Perform the following assertion: :code:`assert isinstance(obj, class_or_tuple)`.

Parameters
-----
obj
    The positional-only argument ``obj`` of :func:`isinstance`<python:isinstance>
    ↪`.

class_or_tuple
    The positional-only argument ``class_or_tuple`` of :func:`isinstance`
    ↪<python:isinstance>`.

Keyword Arguments
-----
invert : :class:`bool`
    If :data:`True`, invert the output of the assertion: :code:`assert not_
    ↪isinstance(obj, class_or_tuple)`.

exception : :class:`type` [:exc:`Exception`], optional
    Assert that exception is raised during/before the assertion operation.

post_process : :data:`Callable[[Any], bool]<typing.Callable>`, optional
    Apply post-processing to the to-be asserted data before asserting_
    ↪aforementioned data.
    Example values would be the likes of :func:`any`<python:any>` and_
    ↪:func:`all`<python:all>`.

message : :class:`str`, optional
    A custom error message to-be passed to the ``assert`` statement.

:rtype: :data:`None`

See also
-----
:func:`isinstance`<python:isinstance>`
    Return whether an object is an instance of a class or of a subclass_
    ↪thereof.

    A tuple, as in ``isinstance(x, (A, B, ...))``, may be given as the target to
```

(continues on next page)

(continued from previous page)

```
check against. This is equivalent to ``isinstance(x, A) or isinstance(x, B)
or ...`` etc.
```

Parameters `func` (Callable) – A callable whose output is to-be asserted.

Returns A new docstring constructed from `funcs`' docstring.

Return type `str`

`assertionlib.functions.bind_callable` (*class_type: Union[type, Any], func: Callable, name: Optional[str] = None, warn: bool = True*) → None

Take a callable and use it to create a new assertion method for `class_type`.

The created callable will have the same signature as `func` except for one additional keyword argument by the name of `func` (default value: `False`). Setting this keyword argument to `True` will invert the output of the assertion, *i.e.* it changes `assert func(...)` into `assert not func(...)`.

Examples

Supplying the builtin `len()` function will create (and bind) a callable which performs the `assert len(obj)` assertion.

Parameters

- **class_type** (`type` or `Any`) – A class (*i.e.* a `type` instance) or class instance.
- **func** (Callable) – A callable object whose output will be asserted by the created method.
- **name** (`str`, optional) – The name of the name of the new method. If `None`, use the name of `func`.

Return type `None`

`assertionlib.functions.to_positional` (*func: FT*) → FT

Decorate a function's `__signature__` such that all positional-or-keyword arguments are changed to either positional- or keyword-only.

Example

```
>>> from inspect import signature
>>> from assertionlib.functions import to_positional

>>> def func1(a: int, b: int = 0) -> int:
...     pass

>>> @to_positional
... def func2(a: int, b: int = 0) -> int:
...     pass

>>> print(signature(func1), signature(func2), sep='\n')
(a: int, b: int = 0) -> int
(a: int, /, *, b: int = 0) -> int
```

2.2.5 assertionlib.assertion_functions

A module with various new assertion functions.

Index

<code>len_eq(a, b, /)</code>	Check if the length of a is equivalent to b : <code>len(a) == b</code> .
<code>str_eq(a, b, /, *, [str_converter])</code>	Check if the string-representation of a is equivalent to b : <code>repr(a) == b</code> .
<code>shape_eq(a, b, /)</code>	Check if the shapes of a and b are equivalent: <code>a.shape == getattr(b, 'shape', b)</code> .
<code>isdisjoint(a, b, /)</code>	Check if a has no elements in b .
<code>issuperset(a, b, /)</code>	Check if a contains all elements from b .
<code>issubset(a, b, /)</code>	Check if b contains all elements in a .
<code>function_eq(func1, func2, /)</code>	Check if two functions are equivalent by checking if their <code>__code__</code> is identical.

API

`assertionlib.assertion_functions.len_eq(a: Sized, b: int, /) → bool`

Check if the length of **a** is equivalent to **b**: `len(a) == b`.

`assertionlib.assertion_functions.str_eq(a: T, b: str, /, *, str_converter: Callable[[T], str] = <built-in function repr>) → bool`

Check if the string-representation of **a** is equivalent to **b**: `repr(a) == b`.

`assertionlib.assertion_functions.shape_eq(a: numpy.ndarray, b: Union[numpy.ndarray, Tuple[int, ...]], /) → bool`

Check if the shapes of **a** and **b** are equivalent: `a.shape == getattr(b, 'shape', b)`.

b should be either an object with the `shape` attribute (e.g. a NumPy array) or a `tuple` representing a valid array shape.

`assertionlib.assertion_functions.isdisjoint(a: Iterable[Hashable], b: Iterable[Hashable], /) → bool`

Check if **a** has no elements in **b**.

`assertionlib.assertion_functions.issuperset(a: Iterable[Hashable], b: Iterable[Hashable], /) → bool`

Check if **a** contains all elements from **b**.

`assertionlib.assertion_functions.issubset(a: Iterable[Hashable], b: Iterable[Hashable], /) → bool`

Check if **b** contains all elements in **a**.

`assertionlib.assertion_functions.function_eq(func1: function, func2: function, /) → bool`

Check if two functions are equivalent by checking if their `__code__` is identical.

func1 and **func2** should be instances of `FunctionType` or any other object with access to the `__code__` attribute.

PYTHON MODULE INDEX

a

- `assertionlib`, 7
- `assertionlib.assertion_functions`, 50
- `assertionlib.dataclass`, 43
- `assertionlib.functions`, 47
- `assertionlib.manager`, 7
- `assertionlib.ndrepr`, 40

Symbols

- `__HASHABLE` (*assertionlib.dataclass.AbstractDataClass* attribute), 44
 - `__PRIVATE_ATTR` (*assertionlib.dataclass.AbstractDataClass* attribute), 44
 - `__call__()` (*assertionlib.manager.AssertionManager* method), 12
 - `__copy__()` (*assertionlib.dataclass.AbstractDataClass* method), 45
 - `__deepcopy__()` (*assertionlib.dataclass.AbstractDataClass* method), 45
 - `__eq__()` (*assertionlib.dataclass.AbstractDataClass* method), 45
 - `__hash__()` (*assertionlib.dataclass.AbstractDataClass* method), 45
 - `__repr__()` (*assertionlib.dataclass.AbstractDataClass* method), 44
 - `__hash` (*assertionlib.dataclass.AbstractDataClass* attribute), 44
- ## A
- `abs()` (*assertionlib.manager.AssertionManager* method), 13
 - `AbstractDataClass` (class in *assertionlib.dataclass*), 44
 - `add()` (*assertionlib.manager.AssertionManager* method), 13
 - `add_to_instance()` (*assertionlib.manager.AssertionManager* method), 12
 - `all()` (*assertionlib.manager.AssertionManager* method), 35
 - `allclose()` (*assertionlib.manager.AssertionManager* method), 30
 - `and_()` (*assertionlib.manager.AssertionManager* method), 13
 - `any()` (*assertionlib.manager.AssertionManager* method), 35
 - `as_dict()` (*assertionlib.dataclass.AbstractDataClass* method), 45
 - `assert_()` (*assertionlib.manager.AssertionManager* method), 11
 - `assertion` (in module *assertionlib.manager*), 11
 - `assertionlib` module, 7
 - `assertionlib.assertion_functions` module, 50
 - `assertionlib.dataclass` module, 43
 - `assertionlib.functions` module, 47
 - `assertionlib.manager` module, 7
 - `assertionlib.ndrepr` module, 40
 - `AssertionManager` (class in *assertionlib.manager*), 11
- ## B
- `bind_callable()` (in module *assertionlib.functions*), 49
- ## C
- `callable()` (*assertionlib.manager.AssertionManager* method), 33
 - `concat()` (*assertionlib.manager.AssertionManager* method), 14
 - `contains()` (*assertionlib.manager.AssertionManager* method), 14
 - `copy()` (*assertionlib.dataclass.AbstractDataClass* method), 45
 - `countOf()` (*assertionlib.manager.AssertionManager* method), 15
 - `create_assertion_doc()` (in module *assertionlib.functions*), 48
- ## E
- `eq()` (*assertionlib.manager.AssertionManager* method), 15

F

`floordiv()` (*assertionlib.manager.AssertionManager* method), 16

`from_dict()` (*assertionlib.dataclass.AbstractDataClass* class method), 46

`function_eq()` (*assertionlib.manager.AssertionManager* method), 39

`function_eq()` (in module *assertionlib.assertion_functions*), 50

G

`ge()` (*assertionlib.manager.AssertionManager* method), 16

`get_sphinx_domain()` (in module *assertionlib.functions*), 47

`getitem()` (*assertionlib.manager.AssertionManager* method), 17

`gt()` (*assertionlib.manager.AssertionManager* method), 17

H

`hasattr()` (*assertionlib.manager.AssertionManager* method), 33

I

`index()` (*assertionlib.manager.AssertionManager* method), 18

`indexOf()` (*assertionlib.manager.AssertionManager* method), 18

`inherit_annotations()` (*assertionlib.dataclass.AbstractDataClass* class method), 46

`inv()` (*assertionlib.manager.AssertionManager* method), 18

`invert()` (*assertionlib.manager.AssertionManager* method), 19

`is_()` (*assertionlib.manager.AssertionManager* method), 19

`is_not()` (*assertionlib.manager.AssertionManager* method), 20

`isabs()` (*assertionlib.manager.AssertionManager* method), 28

`isclose()` (*assertionlib.manager.AssertionManager* method), 31

`isdir()` (*assertionlib.manager.AssertionManager* method), 28

`isdisjoint()` (*assertionlib.manager.AssertionManager* method), 36

`isdisjoint()` (in module *assertionlib.assertion_functions*), 50

`isfile()` (*assertionlib.manager.AssertionManager* method), 29

`isfinite()` (*assertionlib.manager.AssertionManager* method), 31

`isinf()` (*assertionlib.manager.AssertionManager* method), 32

`isinstance()` (*assertionlib.manager.AssertionManager* method), 34

`islink()` (*assertionlib.manager.AssertionManager* method), 29

`ismount()` (*assertionlib.manager.AssertionManager* method), 30

`isnan()` (*assertionlib.manager.AssertionManager* method), 32

`issubclass()` (*assertionlib.manager.AssertionManager* method), 34

`issubset()` (*assertionlib.manager.AssertionManager* method), 37

`issubset()` (in module *assertionlib.assertion_functions*), 50

`issuperset()` (*assertionlib.manager.AssertionManager* method), 36

`issuperset()` (in module *assertionlib.assertion_functions*), 50

L

`le()` (*assertionlib.manager.AssertionManager* method), 20

`len()` (*assertionlib.manager.AssertionManager* method), 35

`len_eq()` (*assertionlib.manager.AssertionManager* method), 38

`len_eq()` (in module *assertionlib.assertion_functions*), 50

`length_hint()` (*assertionlib.manager.AssertionManager* method), 27

`lshift()` (*assertionlib.manager.AssertionManager* method), 21

`lt()` (*assertionlib.manager.AssertionManager* method), 21

M

`matmul()` (*assertionlib.manager.AssertionManager* method), 22

`maxDataFrame` (*assertionlib.ndrepr.NDRepr* attribute), 42

`maxfloat` (*assertionlib.ndrepr.NDRepr* attribute), 41

`maxMolecule` (*assertionlib.ndrepr.NDRepr* attribute), 41

maxndarray (*assertionlib.ndrepr.NDRepr* attribute), 41
 maxSeries (*assertionlib.ndrepr.NDRepr* attribute), 42
 maxSignature (*assertionlib.ndrepr.NDRepr* attribute), 41
 maxstring_fallback (*assertionlib.manager.AssertionManager* attribute), 11
 mod() (*assertionlib.manager.AssertionManager* method), 22
 module
 assertionlib, 7
 assertionlib.assertion_functions, 50
 assertionlib.dataclass, 43
 assertionlib.functions, 47
 assertionlib.manager, 7
 assertionlib.ndrepr, 40
 mul() (*assertionlib.manager.AssertionManager* method), 23

N

NDRepr (*class in assertionlib.ndrepr*), 41
 ne() (*assertionlib.manager.AssertionManager* method), 23
 neg() (*assertionlib.manager.AssertionManager* method), 23
 not_() (*assertionlib.manager.AssertionManager* method), 24
 np_printoptions (*assertionlib.ndrepr.NDRepr* attribute), 42

O

or_() (*assertionlib.manager.AssertionManager* method), 24

P

pd_printoptions (*assertionlib.ndrepr.NDRepr* attribute), 42
 pos() (*assertionlib.manager.AssertionManager* method), 25
 pow() (*assertionlib.manager.AssertionManager* method), 25

R

repr_Atom() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_Bond() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_builtin_function_or_method() (*assertionlib.ndrepr.NDRepr* method), 42
 repr_DataFrame() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_Dataset() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_dict_items() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_dict_keys() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_dict_values() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_Exception() (*assertionlib.ndrepr.NDRepr* method), 42
 repr_fallback (*assertionlib.manager.AssertionManager* attribute), 11
 repr_float() (*assertionlib.ndrepr.NDRepr* method), 42
 repr_function() (*assertionlib.ndrepr.NDRepr* method), 42
 repr_instance (*assertionlib.manager.AssertionManager* attribute), 11
 repr_method() (*assertionlib.ndrepr.NDRepr* method), 42
 repr_method_descriptor() (*assertionlib.ndrepr.NDRepr* method), 42
 repr_module() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_Molecule() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_ndarray() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_Series() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_Settings() (*assertionlib.ndrepr.NDRepr* method), 43
 repr_Signature() (*assertionlib.ndrepr.NDRepr* method), 42
 repr_type() (*assertionlib.ndrepr.NDRepr* method), 43
 round() (*assertionlib.manager.AssertionManager* method), 37
 rshift() (*assertionlib.manager.AssertionManager* method), 26

S

shape_eq() (*assertionlib.manager.AssertionManager* method), 39
 shape_eq() (*in module assertionlib.assertion_functions*), 50
 str_eq() (*assertionlib.manager.AssertionManager* method), 38
 str_eq() (*in module assertionlib.assertion_functions*), 50
 sub() (*assertionlib.manager.AssertionManager* method), 26

T

`to_positional()` (in module *assertionlib.functions*),
49

`truediv()` (*assertionlib.manager.AssertionManager*
method), 27

`truth()` (*assertionlib.manager.AssertionManager*
method), 27